Weather Monitoring System

Code

```
#include <DHT.h> // Include the DHT sensor library
#define DHT11 PIN 4 // DHT11 sensor data pin
#define RAINDROP PIN A0 // Raindrop sensor pin
DHT dht(DHT11 PIN, DHT11); // Initialize DHT11 sensor
void setup() {
 Serial.begin(9600); // Start serial communication at 9600 baud rate
 dht.begin();
                 // Initialize DHT sensor
Serial.println("Weather Monitoring System Started...");
}
void loop() {
// Read the temperature and humidity from the DHT11 sensor
 float temp = dht.readTemperature(); // Get temperature in Celsius
 float humidity = dht.readHumidity(); // Get humidity in percentage
 // Read the raindrop sensor value (analog)
 int raindropValue = analogRead(RAINDROP PIN); // Raindrop sensor value
// Check for DHT11 reading errors
 if (isnan(temp) | | isnan(humidity)) {
  Serial.println("Failed to read from DHT11 sensor.");
  return;
}
```

```
// Print DHT11 sensor readings
 Serial.print("Temperature (DHT11): ");
 Serial.print(temp);
 Serial.print((char)223); // Degree symbol (°)
 Serial.print("C ");
 Serial.print("Humidity: ");
 Serial.print(humidity);
 Serial.println("%");
 // Print Raindrop sensor readings
 Serial.print("Raindrop Sensor Value: ");
 Serial.println(raindropValue);
 if (raindropValue < 500) {
  Serial.println("Rain Detected!");
 } else {
  Serial.println("No Rain.");
 }
 delay(2000); // Wait for 2 seconds before the next loop
}
```